

Access JSOC data from Matlab environments

JSOC contains a large collection of data files. While the data files are store SUMS, the information about the data files are stored in keywords, in DRMS. These keywords are used to describe the content, the hierarchical relationship among these files as well as their current locations. Users can use these keywords to make queries searching for the data they need. JSOC makes these information accessible via a web interface. Where, users can search, check for storage status, make request and download the data files.

JSOC currently provides these functions:

show_series: for listing series name available in JSOC
jsoc_info : for displaying the series structure, record summary,
keywords, values and pseudo keywords.
jsoc_fetch : for requesting for a record set.

These functions can be called directly when we are JSOC network, or over a web interface when we query remotely. These functions can return data inform of JSON objects, which can parsed into Matlab data structures.

Here is some Matlab scripts (.m files) that users can use to query DRMS interactively from Matlab environments. These scripts are also serve as examples, showing how to extract information returned by these functions.

series_list.m : returns series names existing in JSOC
series_struct.m : examines the structure of a data series.
rs_summary.m : returns number of records in a series
rs_list.m : for selectively displaying keywords values, storage status
of a record set.
exp_request.m : for requesting and exporting data files from JSOC to user.

Note:

It is more efficient to call these functions directly when we are on JSOC network (default).
When access remotely, please append 'web_access' to these commands, which will pass the queries through a web interface (<http://jsoc.stanford.edu/cgi-bin/ajax/>)
These scripts use a JSON parser written by F Glineur, download from Matlab Central ([parse_json.m](#))

To run, please copy these .m files (from /home/timh/matlab_jsoc/*.m) to your working directory.
Run matlab, then these commands.
(Perhaps, also setenv MATLAB_SHELL /bin/tcsh before running matlab)

series_list.m
Usage: series_list 'filter_string'

```
>> series_list hmi.lev
hmi.lev0
hmi.lev0TEST_0445_0015
hmi.lev0TEST_0451_0007
...
hmi.lev0b
hmi.lev0c
hmi.lev0d
hmi.lev0e
hmi.lev0e_test
hmi.lev0f
hmi.lev1
lm_jps.hmi_lev0
lm_jps.hmi_lev0_60d
su_production.hmi_lev1e
```

Number of series matched [hmi.lev] = 59

series_struct.m
Usage: series_struct 'series_name'

```
>> series_struct 'hmi.lev0e'
```

Keywords:

ORIGIN

ORIGIN Location where file made

DATE	Date_time of processing; ISO 8601
DATE__OBS	[DATE-OBS] Date when observation started; ISO 8601
T_OBS	Observation time
EXPTIME	Exposure duration: mean shutter open time
TIME	Time of observation: seconds within a day
MJD	Date of observation: modified julian day
TELESCOP	For HMI: SDO/HMI
INSTRUME	For HMI: HMI_SIDE1 or HMI_FRONT2
CAMERA	For HMI: 1 or 2
WAVELNTH	For HMI: 617.33 nm
IMGAPID	Image Application ID
IMGFPT	FIRST_PACKET_TIME
BITSELID	Bit select ID, r
COMPID	Compression ID; n,k
CROPID	Crop table ID
DATAVALS	Actual number of data values in image
FID	FID Filtergram ID
...	
image_bscale	
cparms_sg000	
cparms_sg001	
image_bzero	
image_sm_bzero	
image_sm_bscale	

Segments:

```

image
  name: 'image'
  units: 'dn'
  protocol: 'fits'
  dims: 'VARxVAR'
  note: 'lev0 data fits file'

image_sm
  name: 'image_sm'
  units: 'dn'
  protocol: 'fits'
  dims: 'VARxVAR'
  note: 'lev0 data small fits file with headers'

image_png
  name: 'image_png'
  units: 'dn'
  protocol: 'generic'
  dims: 'VARxVAR'
  note: 'lev0 data sm image'

```

Links:

```

DB Index:
  'FSN'      'T_OBS'

```

Interval:

```

FirstRecord: 'hmi.lev0e[45853]'
FirstRecnum: 404796
LastRecord: 'hmi.lev0e[1879935]'
LastRecnum: 426947
MaxRecnum: 435652

```

ans =

```

  note: 'HMI'
  retention: 60
  unitsize: 1
  archive: 1
  tapegroup: 2
  primekeys: {'FSN'}
  dbindex: {'FSN' 'T_OBS'}
  keywords: {1x86 cell}
  segments: {[1x1 struct] [1x1 struct] [1x1 struct]}
  links: {0x1 cell}
  Interval: [1x1 struct]
  status: 0

```

rs_summary.m
Usage: rs_summary 'series_name'

```
>> rs_summary 'hmi.lev0e'  
      count: 110591  
      status: 0
```

rs_list.m
Usage: rs_list query_string

```
>> rs_list 'hmi.lev0e[1800000-1800010] key=T_OBS,FSN'
```

Keywords:

T_OBS
FSN

2008.09.07_06:22:22.21.UTC	1800000
2008.09.07_06:22:24.21.UTC	1800001
2008.09.07_06:22:26.22.UTC	1800002
2008.09.07_06:22:28.21.UTC	1800003
2008.09.07_06:22:30.23.UTC	1800004
2008.09.07_06:22:32.22.UTC	1800005
2008.09.07_06:22:34.23.UTC	1800006
2008.09.07_06:22:36.23.UTC	1800007
2008.09.07_06:22:38.23.UTC	1800008
2008.09.07_06:22:40.16.UTC	1800009
2008.09.07_06:22:42.16.UTC	1800010

Records found 11

ans =

```
      keywords: {[1x1 struct] [1x1 struct]}  
      segments: {0x1 cell}  
      links: {0x1 cell}  
      count: 11  
      status: 0
```

```
>>a=rs_list('hmi.lev0e[1800000-1800001] key=T_OBS,FSN,*online*,*sunum*,*recnum*,*size*,*retain*,  
*logdir*');
```

Keywords:

T_OBS
FSN
online
sunum
recnum
size
retain
logdir

2008.09.07_06:22:22.21.UTC	1800000 N	10104055.000000	299574.000000	12786184	N/A
No log available					
2008.09.07_06:22:24.21.UTC	1800001 N	10103997.000000	299557.000000	12751824	N/A
No log available					

Records found 2

To get the segment names (file paths) of a record set, we can do this

```
>> a = rs_list('hmi.lev0e[1800000-1800010] key=**NONE** seg=**ALL**');
```

Keywords:

Records found 11

Segments:

```
      image  
      name: 'image'  
      values: {1x11 cell}  
      dims: {1x11 cell}  
      image_sm
```

```
name: 'image_sm'
values: {1x11 cell}
dims: {1x11 cell}
```

```
image_png
name: 'image_png'
values: {1x11 cell}
dims: {1x11 cell}
```

Links:

```
>> a.segments{3}.values{1}
ans =
/SUM0/D21848888/D10104055/S00000/image.png
```

```
rs_online_check.m
Usage: rs_online_check 'query_string'
```

```
>> b=rs_online_check('su_production.lev0f_hmi[706300-706500]');
Found 15 records, (all) online = Yes, size = 2136654490
```

```
exp_request.m
Usage: exp_request 'query_string'
```

```
>> a=exp_request('su_production.lev0f_hmi[706315]{image}');
count: 1
size: 14002560
dir: [1x0 char]
data: {[1x1 struct]}
requestid: [1x0 char]
method: 'url_quick'
protocol: 'as-is'
wait: 0
status: 0
```

<http://jsoc.stanford.edu//SUM1/D21527735/S00009/image.fits>

image.fits downloaded!

```
>> a=exp_request('su_timh.supersid_test_data_3[][NAA][]');
count: 1
size: 620477
dir: [1x0 char]
data: {[1x1 struct]}
requestid: [1x0 char]
method: 'url_quick'
protocol: 'as-is'
wait: 0
status: 0
```

http://jsoc.stanford.edu//SUM3/D19153270/S00000/WSO_NAA_2009-03-02.csv

WSO_NAA_2009-03-02.csv downloaded!


To query JSOC remotely

When we are not on JSOC network, we still can query similarly by appending 'web_access' to above commands. They will be passed through the web interface <http://jsoc.stanford.edu/cgi-bin/ajax/>


```
>> series_list('hmi.lev','web_access')
>> series_struct('hmi.lev0e','web_access')
>> a=rs_list('hmi.lev0e[1800000-1800001] key=T_OBS,FSN,*online*,*sunum*,
*recnum*,*size*,*retain*,*logdir*', 'web_access');
```

Here are some useful commands to display a FITS file or plot a SID file.

```
>> fitsinfo('image.fits');  
>> fitsinfo('coffee_cup_sunspot.fits');  
>> handle = fitsread('coffee_cup_sunspot.fits');  
>> imagesc(handle);
```



```
>> s = csvread('WSO_NAA_2009-03-02.csv',11,1);  
>> plot(s);
```



To display the FITS header:

For instance, we would like to check whether the file is compressed or not, here are 2 examples, examining the FITS file headers.

Example1:

coffee_cup_sunspot.fits is an uncompressed FITS file, which contains 1 HDU 'PrimaryData'. This HDU has 183 keywords, DataSize = 4194304.

```
>> h= fitsinfo('coffee_cup_sunspot.fits')
h =
    Filename: 'coffee_cup_sunspot.fits'
    FileModDate: '18-Nov-2009 10:05:52'
    FileSize: 4213440
    Contents: {'Primary'}
    PrimaryData: [1x1 struct]

>> h.PrimaryData
ans =
    DataType: 'single'
    Size: [1024 1024]
    DataSize: 4194304
    MissingDataValue: []
    Intercept: 0
    Slope: 1
    Offset: 17280
    Keywords: {183x3 cell}

>> h.PrimaryData.Keywords
ans =
    'SIMPLE'      'T'                [1x48 char]
    'BITPIX'      [          -32]          ''
    'NAXIS'       [           2]          ''
    'NAXIS1'      [          1024]         ''
    'NAXIS2'      [          1024]         ''
    ...
    'DSNAME'      [1x47 char]           ''
    'PROTOCOL'    'RDB.FITS'            ''
    'DSDS_UID'    [           0]         ''
    ...
```

Example 2:

mdi.fd_M_96m_lev18.141166.data.fits is a compressed FITS file, which has 2 HDU:

- PrimaryData contain only a few standard keywords without data.
- BinarayTable has the first keyword 'XTENSION' = 'BINTABLE', with data.

```
>> h=fitsinfo('mdi.fd_M_96m_lev18.141166.data.fits')
h =
    Filename: 'mdi.fd_M_96m_lev18.141166.data.fits'
    FileModDate: '18-Nov-2009 10:14:45'
    FileSize: 1451520
    Contents: {'Primary' 'Binary Table'}
    PrimaryData: [1x1 struct]
    BinaryTable: [1x1 struct]

>> h.PrimaryData
ans =
    DataType: 'int16'
    Size: []
    DataSize: 0
    MissingDataValue: []
    Intercept: 0
    Slope: 1
    Offset: 2880
    Keywords: {7x3 cell}

>> h.BinaryTable
ans =
    Rows: 1024
    RowSize: 8
    NFields: 1
    FieldFormat: {'1PB(4134)'}
    FieldPrecision: {'int32'}
    FieldSize: 2
    DataSize: 8192
    MissingDataValue: {[ ]}
    Intercept: 0
    Slope: 1
    Offset: 5760
```

```

ExtensionSize: 1435085
ExtensionOffset: 13952
Keywords: {26x3 cell}

```

```
>> h.PrimaryData.Keywords
```

```
ans =
'SIMPLE'      'T'      [1x48 char]
'BITPIX'      [16]     [1x48 char]
'NAXIS'       [ 0]     [1x48 char]
'EXTEND'      'T'      [1x48 char]
'COMMENT'     ''       [1x72 char]
'COMMENT'     ''       [1x72 char]
'END'         ''       ''
```

```
>> h.BinaryTable.Keywords
```

```
ans =
'XTENSION'    'BINTABLE'      [1x48 char]
'BITPIX'      [          8]    [1x48 char]
'NAXIS'       [          2]    [1x48 char]
'NAXIS1'      [          8]    [1x48 char]
'NAXIS2'      [        1024]    [1x48 char]
'PCOUNT'      [    1435085]    [1x48 char]
'GCOUNT'      [          1]    [1x48 char]
'TFIELDS'     [          1]    [1x48 char]
'TTYPE1'      'COMPRESSED_DATA' [1x48 char]
'TFORM1'      '1PB(4134) '     [1x48 char]
'ZIMAGE'      'T'              [1x48 char]
'ZBITPIX'     [          32]    [1x48 char]
'ZNAXIS'      [          2]    [1x48 char]
'ZNAXIS1'     [        1024]    [1x48 char]
'ZNAXIS2'     [        1024]    [1x48 char]
'ZTILE1'      [        1024]    [1x48 char]
'ZTILE2'      [          1]    [1x48 char]
'ZCMPTYPE'    'RICE_1'         [1x48 char]
'ZNAME1'      'BLOCKSIZE'      [1x48 char]
'ZVAL1'       [          32]    [1x48 char]
'ZNAME2'      'BYTEPIX'        [1x48 char]
'ZVAL2'       [          4]    [1x48 char]
'BLANK'       [    -2.1475e+09] ''
'BZERO'       [          0]    ''
'BSCALE'      [      0.0100]   ''
'END'         ''              ''
```

MFITSIO

From the above examples, we saw that, when the FITS file is compressed, the BITPIX, NAXIS, NAXIS1, NAXIS2 values do not reflect the actual image's data type and dimensions. And, data array returned is not readily usable.

```

'BITPIX'      [          8]    [1x48 char]
'NAXIS'       [          2]    [1x48 char]
'NAXIS1'      [          8]    [1x48 char]
'NAXIS2'      [        1024]    [1x48 char]

```

Currently out of the box, Matlab provides only 2 functions to read FITS uncompressed files into Matlab:

```

fitsinfo() to return HDU header
fitsread() to return HDU data

```

From CFITSIO main page (www.heasarc.gsfc.gov/fitsio/), it is recommended to use MFITSIO developed by Damina Eads at Los Alamos National Laboratory.

MFITSIO (<http://public.lanl.gov/eads/mfitsio/>) provides a few more functions:

```

fits_read_header()
fits_write_header()
fits_delete_keyword()
fits_read_image()
fits_write_image()
fits_read_image_subset()
fits_write_image_subset()

```

These allows users to read/write FITS header and data.

However, most FITS images stored SUMS are as Rice compressed format. For efficiency, we added these 2 functions allow users to directly read compressed file in SUMS.

`fits_read_header_compress()` which returns the correct (uncompressed) image's type and dimensions
`fits_read_image_compress()` which returns the uncompressed image in mxArray ready for use.

To use these functions in matlab, we can add path to (/home/timh/matlab_jsoc/mex/) then call these functions like this.

```
>> path(path, '/home/timh/matlab_jsoc/mex')
>> a=fits_read_header_compress('coffee_cup_sunspot.fits');
>> a
a =
    BITPIX: -32
    NAXIS: 2
    NAXIS1: 1024
    NAXIS2: 1024
    .....
    DSNAME: 'prog:mdi,level:lev1.8,series:fd_M_96m_01d[1994]'
    PROTOCOL: 'RDB.FITS'
    DSDS_UID: 0
    CONFORMS: 'TS_EQ'
    .....

>> b=fits_read_image_compress('coffee_cup_sunspot.fits');
>> imagesc(b)
```

For example: image.fits is a compressed image.

Here, we use

`fits_read_header()` to inspect the HDU keywords and data.
`fits_read_header_compress()` to acquire header and data for use.

Note:

HDU 0 does not contain any data

HDU 1 contains keywords which does not reflect the actual (uncompressed) dimensions of the image.

`fits_read_header_compress()` filters out ("Z" structure) keywords and return only the user's keywords along with BITPIX, NAXIS, NAXIS1, NAXIS2 as of actual, uncompressed image.

```
>> a=fits_read_header('image.fits[0]')
a =
    BITPIX: 16
    NAXIS: 0

>> a=fits_read_header('image.fits[1]')
a =
    XTENSION: 'BINTABLE'
    BITPIX: 8
    NAXIS: 2
    NAXIS1: 8
    NAXIS2: 4096
    PCOUNT: 8001556
    GCOUNT: 1
    TFIELDS: 1
    TTYPE1: 'COMPRESSED_DATA'
    TFORM1: '1PB(2438)'
    ZIMAGE: 1
    ZBITPIX: 16
    ZNAXIS: 2
    ZNAXIS1: 4096
    ZNAXIS2: 4096
    ZTILE1: 4096
    ZTILE2: 1
    ZCMPTYPE: 'RICE_1'
    ZNAME1: 'BLOCKSIZE'
    ZVAL1: 32
    ZNAME2: 'BYTEPIX'
    ZVAL2: 2
    BLANK: -32768
```

```
>> a=fits_read_header_compress('image.fits[1]')
a =
    BITPIX: 16
```


NAXIS: 2
NAXIS1: 4096
NAXIS2: 4096
BLANK: -32768

```
>> d=fits_read_image_compress('image.fits[1]');  
>> imagesc(d)
```